


Customizing Map Labels

The concentration display menu only contains a “mass label” entry that can be used to customize map labels. This changes the text on the second line for the mass units of concentration. This would normally be used in conjunction with the concentration multiplier if for instance emission units were grams but display units of micro-grams were desired. Additional label information can be changed if the concentration display program finds a file called “[LABELS.CFG](#)” as shown in the adjacent graphic taken from the previous example.



Supplemental text information can be added at the bottom of each plot by entering information on the “Extra Label” menu called from the “Advanced” menu tab. This creates a file called “[MAPTEXT.CFG](#)” which is read by both the trajectory and concentration plotting programs.

